PRND Equipment for CM mission

Project Overview

- Mission/SOW:
 - Categorize PRND equipment for use in CM mission
 - Assist local first responder leadership to better use equipment
- Expected outcomes:
 - Tool to be used by local first responder leadership to size up current inventory
 - Copy/paste verbiage for policies and procedures
- Period of performance: 2 years beginning 9/2015

Major Milestones

- Task 2: In progress
 - Review current applicable standards
 - Create categories for equipment (ranges and limitations)
 - Completion anticipated: End of January
- Task 3:
 - Document Consequence Management Relevant Mission Space
 - Conduct webinars to solicit interagency feedback
- Task 4:
 - Develop CONOPS for CM Missions using categorized PRND equipment
- Task 5:
 - Scientifically validate CONOPS
 - Lab and field test
- Task 6:
 - Develop actionable knowledge products and training for first responders

December Meeting

- Overview of current categorization scheme
- Brainstorm session
 - Importance factors for CM
 - Attempts at categorization

Brooke Buddemeier, LLNL Chuck Finfrock, BNL Al Goodwyn, SRNL RaJah Mena, CM Consultant Frank Moore, RAP Region 5 Steve Musolino, RAP Region 1 and BNL support Alexis Reed, CTOS Dave Trombino, RAP Region 7 Don Van Etten, CTOS and CM Consultant


Typical types of equipment used by responders in initial response

In order of likelihood:

- Survey meters (hot dog GM, ion chamber, uR meter)
- Contamination meters (e.g., pancake GM)
- Self Reading dosimeter (Non-Alarming PERD)
- Personal Radiation Detector (PRD)
- Personal Emergency Radiation Detector (PERD)
- Electronic Dosimeter
- Passive Dosimeter
- Radio-Isotope Identification Device (RIID)
- Other?

Manufactur Vendor	•	Model	V		[Draft] NIMS Type	Weight (oz)	Dimensions (LxWxH in)	IP Rating, Water Tightness		Temp range (F√	Battery ty 🔻		ery Life		P (Gamma Detector 1 (High sensitivity) Cesium	Gamma 2 Detector (High Range	
BNC		NukeAlert 95	1		Type 2	6.4	4 3.75 x 2.5 x 1.25	IP54, Watertigh	nt"	-10 to 122	2 AA		ears @ s/week	10 Years Min		Iodide Scintillator	No]
BNC		PalmRAD SPR	RD 920		Type 2	24.	7 5.71 x 3.94 x 1.	IP54, Wate 97 splash		-4 to 122 -59.8 to		≥ 14	h	10 Years	- 1	Scintillator Nal	GM Tube	
Canberra		nufacturer/ ndor 🔻	Model		Image	(de	mma Readout efined swers only)	Gamma Energy Range	Do	tal Gamma ose Rate nge	Maximu		Maxii Do		Adus po Do	mber of stable set sints for se Rate Alarm	Number of Adjustable set points for Dose Alarn	Data Logging (defined answers only) automatic or manual
Canberra	BNO	:	NukeA	lert 951		1-		Down to 20 keV	1	035 mR/h to L mR/h	13 mRem	n/hr	N/	/A		1	N/A	<u>No</u>
D-Tect	Can	berra	erra UltraRadiac Plus		750	Re (G		I		1 uR/h to 500 R/h <u>500R</u>		n <u>r</u> 999 R		<u>9 R</u>	<u>2</u>		<u>2</u>	
D-Tect	D-T	ect	mini-R	adDX		Re	m (Sv) and 1-9		mF	uR/h to 70 R/h	70 mRem	<u>1/hr</u>	N	0		<u>4</u>	None	
Mirion	D-T	ect	mini-R	adD	B	1-	9	30 keV to 3 MeV	1	035 mR/h to L mR/h	1.1 mRen	n/hr	N/	′A		1	N/A	<u>No</u>
	The	ermo	RadEye	e G	O S O		<u>m (Sv)</u>	45 keV to 1.3 MeV	5 u	ur/h to 10 h	<u>10 R/ł</u>	<u>1</u>	N/	/A		<u>2</u>	<u>2</u>	<u>Automatic</u>

Exposure Rate Range



DNDO Alignment

- Current DNDO NIMS Typing only Defines:
 - PRD
 - Type 2 (gamma)
 - Type 1 (gamma/neutron)
 - RIID
 - Type 2 (Low/Med resolution)
 - Type 1 (High Resolution)
 - Backpack
 - Type 4 (gamma)
 - Type 3 (gamma + RIID)
 - Type 2 (gamma/neutron)
 - Type 1 (gamma/neutron + RIID)



Domestic Nuclear Detection Office

Typed Resource Definitions Preventive Radiological/Nuclear Detection (PRND) Resources

October 2014

DNDO Document Number 400-INT-115300v2.1

OCT 2014

PREVENTIVE RADIOLOGICAL/NUCLEAR DETECTION

- Vehicle Mounted
 - Type 4 (gamma)
 - Type 3 (gamma + RIID)
 - Type 2 (gamma/neutron)
 - Type 1 (gamma/neutron + RIID)

Factors Important in CM

Helps to Have:

- Track integrated exposure / Dose
- Alarm at exposure rate set points > 1 mR/h
- Alarm at integrated exposure set points
- Strong /Loud Vibration/Audible Alarm
- Rugged construction
- Change parameters / set points in the field
- Read out in Dose Rate
- Battery Change
- Field Readable
- Geo-reference / Data logging
- Ease to Decon (IP 67)
- Short Over-range recovery time

Should Not:

- Auto Adjust Background (at mrem/hr levels)
- Over-Range to Zero
- Long time to alarm

Big Picture Detection/ Measurement Missions

- Event Recognition / Clearance
- Contamination Footprint Characterization
 - Model normalization
 - Transportation corridors
 - PAG/PAR
 - Establish Control zone / Staging / Reception center locations
- Worker Safety
 - Critical infrastructure / Agricultural
 - Public Health and Lifesaving Activities
- Mass Care
 - Population monitoring & decontamination
- Public Health and Medical
 - Uptake / Exposure indication

Next Steps...

921 ⊕ TABLE 3.2—Mission-oriented detector selection.^a

Mission	Alarming Dosimeter	PRD	PERD	Survey Meter Type-1	Survey Meter Type-2	RID	Backpack	Mobile	Aerial	Portal Monitor	Sensor Networks	Medical Instrumen- tation ^b	Smart Phone App
Shelter/Evacuation Recommendations													
Confirmation of Nuclear Yield	•	0	•	0	•	0	0	0	•	0	0	_	_
Location of Ground Zero	_	_	•	_	•	_	_	_	•	_	0	_	_
Yield Estimation	_	_	•	0	•	_	_	_	•	_	•	_	_
Survey of Dangerous Radiation Zone	•	_	•	0	•	_	_	_	•	_	0	_	_
Dose Monitoring at Shelters	•	0	•	0	•	0	0	0	_	0	_	_	_
Location of Safest Evacuation Routes	•	•	•	•	•	0	0	0	•	_	0	_	_